## **Strawberry Pre-Plant Considerations**



Mark Hoffmann

#### Department of Horticultural Science





#### Overview

- Step 1: Land Preparation: Soil sampling, Varieties, Nutrition, Drainage, Cold spots, Erosion!
- Step 2: Pre Plant: Pre-plant herbicides, Fumigation, Plastic
- Step 3: Transplanting: Bare-root vs. plug plants
- Step 4: Post Transplant: First few months
- **Step 5: Dormancy:** Cold Protection during dormancy
- Spring: Tissue Sampling

## Land-Preparation- General Considerations **NC STATE**

- Windbreaks in north/northwest of field
- Can you crop rotate?
- Row orientation: Soil drainage first. North-South second.
- Wildlife (deer, rabbits, turkey, birds, etc.): Fences!



#### Step 1: Air-Drainage





#### Step 1: Land-Preparation: Soil

NC STATE UNIVERSITY

- Soil Content: Sandy Loam/clay-loam!
- Soil pH: 6.0-6.5



## Step 1: Land-Preparation (3 months before transplanting)

- Disk the ground
- Get your soil tested and follow recommendations!
- Use lime (Ca CO<sub>3</sub>) if pH is too low
- Look at Effective Calcium Carbonate Equivalent (ECCE)

Liming material	Neutralizing agent	CaCO <sub>3</sub> equivalent of pure material (%)		
Dolomitic limestone	CaCO <sub>3</sub> •MgCO <sub>3</sub>	110–118		
Papermill lime sludge	Mainly CaCO <sub>3</sub>	*		
Marl	Mainly CaCO <sub>3</sub>	variable		
Calcitic limestone	CaCO3	100		
Water treatment lime waste	CaCO3	variable		
Wood ash	K <sub>2</sub> CO <sub>3</sub> , CaCO <sub>3</sub> , MgCO <sub>3</sub>	20-90		
Fly ash	CaO, Ca(OH) <sub>2</sub> , CaCO <sub>3</sub>	variable		
Hydrated lime	Ca(OH) <sub>2</sub>	135		
Air-slaked lime	Ca(OH) <sub>2</sub> + CaCO <sub>3</sub>	100-135		

NC STA

## Step 1: Land-Preparation (3 months before transplanting)



- Low soil pH is the most significant problem at this stage in NC.
- This problem <u>cannot be corrected in a timely</u> <u>manner</u> if the crop has already been planted.

## Step 1: Land-Preparation (3 months before transplanting)



 Sampling depth: 8 inches!



## Step2: Pre-Plant (3-0 months before transplanting)

- Order transplants and supplies
- Subsoiling
- Break up soil clods



## NC STATE UNIVERSITY

## Step2: Pre-Plant (3-0 months before transplanting)

- Assemble Irrigation System
- Irrigate for fumigation
- Rotovate for fumigation
- Prebed, if you can!
- Preplant fertilizer
- Preplant fumigations
- Lay plastic
- Drip Tape
- Seed ryegrass in aisles (EROSION)!



**NC STATE** 

UNIVERSITY

## Step2: Pre-Plant Pre-Plant Fertilizer



NCDA&CS Ag	ronomic Divi:	lon	Phone:	(919)73	3-2655	We	b site: ww	w.ncagr	.gov/ag	ronomi/						1	Report	No: 1	3086		
Grower: Copies To: Serving N.C. RESIDENTS FOR OVER 60 YEARS Farm: CEFS																					
Received: 1	0/27/2010	С	omplete	d: 11/2	23/2010		Links to	Helpfi	ul Infor	mation	Wayn	e County									
Agronomist	Agronomist Comments							<u>18, \$</u>													
Field Inform	ation		Applied	l Lime	Recom	mend	ations														
Sample No.	Last Cro	þ	Mo Y	r T/A	Crop or	Year				Lime	N	P205	K20	M	g S	Сц	Zn	B	Mn	See Note	
C2542					1st Crop	: :	Strawberry,E			0	30-60	0	0	(	) ()	0	0	1.0	pH\$	18	
					2nd Cro	p: s	Strawberry,N	I		0	60-80	0	0	(	) (	0	0	1.0	pH\$	18	
Test Results																					
Soll Class	HM% W	/V	CEC	BS%	A	þĦ	P-1	K-1	Ca%	Mg%	Mn-I	Mn-AI(1)	Mn-AI(2)	Zn-I	Zn-AI	Cu-I	S-1	SS-	I NO3-N	NH4-N	Na
MIN	0.32 1.	29	8.0	95.0	0.4	6.5	252	128	72.0	14.0	329	200	200	215	215	130	188		5.0		0.1



## Step2: Pre-Plant Pre-Plant Fertilizer

#### Based on your soil samples Send soil samples to <u>www.ncagr.gov/agronomi/sthome.htm</u> Broadcast fertilizers

*Fertilizer rule of thumb:* 

- Half the Nitrogen (ca. 60 lbs/A)
- All the Phosphorus (ca. 60 lbs/A)
- All the Potassium (ca. 120 lbs/A)
- Too much N will likely produce excess vegetative growth and set fewer fruit.
- Consider applying sulfur
- 15-20 lbs/A sulfur
- 1 − 2 lbs/A of Boron!

#### NC STATE UNIVERSITY

## Step2: Pre-Plant Pre-Plant Fertilizer

Commonly used pre-plant fertilizers:

6-6-18; 6-3-18; 10-5-23: S Source vs. Cl Source of Nitrogen

Phosphate:

- Phosphate-Diammonium phosphate (DAP, 18-46-0)
- Triple superphosphate (0-46-0)

Potassium:

- Potash-potassium nitrate (13-0-44)
- Potassium Sulfate or Chloride

Nitrogen:

- DAP (18-46-0)
- Ammonium sulfate (21-0-0)
- Potassium Nitrate (13-0-44)

#### Step2: Pre-Plant: Plasticulture



Planting Space based on: Variety, Experience and Vigor of plant

- 12 Inches = 17,500 plants/A
- 14 Inches = 15,000 plants/A
- 15 Inches = 14,000 plants/A



Figure 9: Finished Strawberry Bed

## Step2: Pre-Plant: Plasticulture

- With 60 Inch center: 8712 linear feet / A
- Use a 64-66 Inch plastic roll!!
- Use deep bed shaper
- Pre-bedding?



NC STATE

#### **Short-Day Varieties**

#### NC STATE UNIVERSITY

- Chandler
- Camarosa
- Sweet Charlie
- Rocco (NC State variety): Short-day. Early season. Potentially a Sweet Charlie alternative.
- Liz (NC State variety): Short-day. Mid-late season. Potentially a Camarosa alternative.
- **Ruby June (Lassen Canyon variety):** Short-day. Mid-season. Potentially a Chandler alternative.
- Merced (UC variety): Short-day. Mid-season.
- Camino Real (UC variety): Short-day. Early-mid season.

**Recommendations:** 

- Try a few 100 plants of a new variety
- Rely on min two different plant sources if possible

## Step2: Pre-Plant Drip Irrigation

#### NC STATE UNIVERSITY

Recommended: 1 or 2 drip lines per bed,

1 drip line: center 10-12 Inch emitters

2 drip lines: one per side, about 3-2 Inches from the center (requires a straight, bed without clods)



Usually done: One drip line in the bed center

#### Step2: Pre-Plant Plastic Mulch



Plastic	Costs	Fumigant efficacy	Control efficacy
PE Films	Cheap	Not good	
Metalized Films	More costly	better	May control insects by distraction (may affect soil temperature)
VIF	Costly	better	
TIF	Costly	good	

#### Step2: Pre-Plant Plastic Mulch



Plastic	Costs	Pathogens	Insects (high tunnel?)
PE Films	Cheap	low	low
Metalized Films	More costly	low	May control insects by distraction (may affect soil temperature)
VIF	Costly	Low-medium	
TIF	Costly	Medium-high	

#### Step2: Pre-Plant Plastic Mulch



NC STATE UNIVERSITY



UCDAVIS UNIVERSITY OF CALIFORNIA

Ruijun Qin (USDA-ARS) Suduan Gao Husein Ajwa David Sullivan Dong Wang Bradley D. Hanson: Journal of Environmental Quality Abstract 2011, 40 (4), 1195-1203

Fig. 2. Concentration changes of 1,3-dichloropropene (1,3-D) in soil profile in the soil-gas phase in polyethylene (PE)- and totally impermeable film (TIF)-covered fields. The legend shows sampling time (h) after fumigant application.

Fumigants

Pic-Clor 60/80 (300-350 lbs/a, 14-21 days)
 Chloropicrin (60/80%) + 1,3D (40/20%)
 Telone (30-40 gal/a, 21 days)
 Chloropicrin (17-35%) + 1,3-D (65%)

Paladin (14 days)
 Chloropicrin (21%) + Di-Methyl Disulfide (79%)
 Vapam/Kpam/Sectagon and others
 Metam Sodium

#### Step2: Pre-Plant Fumigants

NC STATE UNIVERSITY

'Bio'Fumigants

#### Dominus

Allyl Isothiocyanate (AITC, synthetic; 200-350 lbs/a)

#### Mustard

Allyl Isothiocyanate (AITC, natural)

#### Mustard Seed Meal and Pelleted Mustard Allyl Isothiocyanate (AITC, natural)

# Arugula Nematode Control

#### Fumigants



#### Fumigant and activity

Fumigant	Nematode	Disease	Nutsedge	Other weeds
Telone C 35 + VIF/TIF	+++++	+++++	+++	+++
Telone C 35	+++++	+++++	+	+
In-Line	+++++	+++++	+	+++
Metam Sodium	++	+++	++	+++++
Dominus	++	+++	++	+++
Pic-Clor 60	+++++	+++++	+	+++
Chloropicrin	+	+++++	-	-



#### Respirator

#### NC STATE UNIVERSITY



- Fit Test!
- Medical Exam
- Make sure it forms a seal
- Store at dry and cool place (not in garage/shop)
- Clean regularly
- Change cartridge regularly
- Never use a cartridge AFTER expiration date

#### Fumigants

#### NC STATE UNIVERSITY

Equipment	Cost
Full Face Respirator	\$ 150 – 200
Cartridge	\$ 30 – 50 (frequent costs)
Chemical resistant gloves	\$ 20 – 40 / pair (frequent costs)
Rubber Boots	\$ 20 – 60 / pair
TiVac	\$ 20 – 30 / piece (frequent costs)
TOTAL	\$ 170 – 230 one time
	\$ 70 – 120 frequent

#### Fumigants: look at label!!!!



Fumigant	Short-Term Exposure	Long-Term Exposure
Chloropicrin	Sever irritation of skin, eyes, respiratory tract	Long-lasting Nausea, vomiting, diarrhea
	Difficulty breathing, Headache, Nausea	Affects respiratory tract
1,3 Dichloropropene	Chest Pain, breathing difficulties	Nasal tract, respiratory tract, Urinal bladder
		Maybe carcinogen

#### NC STATE UNIVERSITY

#### Step 1: Calculate the rate of fumigant per 'row acre'

#### 'row acre' =

Number of linear feet of row that equal one acre of ground



#### NC STATE UNIVERSITY

#### **Step 1:** Calculate the rate of fumigant per 'row acre'

'row acre' =

43,560 sqft / row spacing





Step 1: Calculate the rate of fumigant per 'row acre'

**Example: Row-Spacing is 5 feet** 

43,560 sqft / 5 = 8,712 linear ft of rows = 1 acre!!!

100 rows x 200ft = 20,000 linear ft

Row acres = 20,000 / 8,712 = 2.29 acres

Row acres = 100 rows are equivalent to 2.29 acres



Step 2: Calculate Broadcast equivalent rate

# Total amount of fumigant applied to the treated area (ROWS) divided by the TOTAL LAND

- Total area within the perimeter of the fumigated part of the field
- Pounds/gallons of product per treated acre (rate of product applied in the bed)
- Total treated area: Bed with (bottom), row spacing

#### NC STATE UNIVERSITY



#### Step 2: Calculate Broadcast equivalent rate

- Bed with at bottom
- Row spacing
- Product applied per treated area
- Application block size
- Ditch size

#### NC STATE UNIVERSITY

Step 2: Calculate Broadcast equivalent rate

Example:

- Bed with at bottom: 32 inches
- Row spacing: 60 Inches
- Product applied per treated area: 350 lbs
- Application block size: 5 acres
- Ditch size 0.25 acres

Size of beds and furrows (without ditches) = 5 acres – 0.25 acres = 4.75 acre



Step 2: Calculate Broadcast equivalent rate

Example:

Size of beds and furrows (without ditches)

= 5 acres – 0.25 acres = 4.75 acre

Divide the bed width at the bottom by the row spacing = 32 Inches / 60 Inches = 0.53

Determine the **proportion** of the application block to be treated

= 4.75 acres / 5 acres = 0.95

0.53 \* 0.95 \* 350 lbs/A = 176.22 lbs (Broadcast equivalent rate)





# Aim: Measuring and adjusting equipment performance

- Check with your equipment service (e.g. TriEst)
- Technique varies from equipment to equipment

#### NC STATE UNIVERSITY

#### **Flow Meter**

- Usually calibrated for water!
- Higher density = slower movement!!!

Fumigant	Boiling point (°F)	Specific gravity*	Vapor pressure (mm Hg at 20°C)**
1,3-Dichloropropene	219	1.21	34
Chloropierin	234	1.65	18
MITC (dazomet, metam potassium, metam sodium)	246	1.06	13
Methyl bromide	38	1.73	1420
Dimethyl disulfide	229	1.05	17

of water.

"mm Hg = millimeters of mercury.

#### NC STATE UNIVERSITY

#### **Flow Meter**

Must be corrected!

Example:

- Swath width of the rig is 6 feet

#### Determine the time to treat an acre:

- 100 foot rig test: 22 sec. for 600 sqft (6 \* 100)
- 22 sec. / 600 sqft = 0.036 sec./sqft
- 0.036 sec./sqft x 43,560 sqft/ac = 1568 sec./acre = 26.1 min/acre

#### NC STATE UNIVERSITY

#### **Flow Meter**

Must be corrected!

Example:

- Time to treat an acre = 26.1 min
- 100 % flow rate (Water) = 2 gal/min
- Telone EC (93.6 % 1,3D) = 2 x 0.913 = 1.83 gal/min
- 20 gal/a

#### **Determine the flow meter setting**

- Total gal/acre = 26.1 min \* 1.83 gal/min = 47.7 gal (100%)
- FlowMeter (water): (20/47.7) \* 100 = 41.9%



- Let professional service check your equipment service (e.g. TriEst)
- Let them help you calibrate your equipment
- Let them help you advising on fumigation rates and plastic choice

## Step3: Transplanting



- There are two types of plants
  - Bare roots (fresh dugs)
  - Plug Plants
- Water source and labor availability are factors in choosing plant types most suitable for your operation (fresh dugs>plugs)







## Step3: Transplanting

#### NC STATE UNIVERSITY

Fresh dugs v. plugs

- less expensive
- more water to establish
- planting depth tricky
- Plugs easy to plant
- Easy to punch holes with plugs

#### Step3: Transplanting

#### NC STATE UNIVERSITY



#### Bare roots/ cut offs/ fresh dugs: plant earlier than plugs Irrigate after transplanting!

#### Total costs transplanting: approx. \$ 4,000 /A

## Step4: Post-Transplant

Replant (2%)

**Disease and Pest Control:** 

- Ridomil Gold EC (drip system)
- Anthracnose Spray
- Mites
- Botrytis crown rot

Deer/Turkey control?

Runner Removal (ca. 4-5 weeks after transplant)

Total costs: approx. \$600/A



#### NC STATE UNIVERSITY

## Step5: Dormancy

Clean and hand-weed beds

Remove runners

**Disease control (Captan)** 

Apply floating row covers!!!!

Order supplies for Spring



Row covers are applied and removed based on weather

Remove dead foliage and weeds in early Spring

Total Costs: approx. \$ 2,400/A (row covers: \$1,300/A)

#### NC STATE UNIVERSITY

#### Step5: Dormancy

#### NC STATE UNIVERSITY

Row covers:

- Can be used to increase flowering buds
- Used to frost protect (min temperatures < 22F in dormancy)



#### Step5: Dormancy: Cold Damage





## Step6: Pre-Harvest

#### NC STATE UNIVERSITY

- Tissue Sampling (bi weekly)
- Pull plants and weeds
- Fertilize (.75 lbs N/day)
- Scout for pests (mites?)
- Botrytis control
- Powdery Mildew control
- Pollinate with bees!!!!!
- Fireants
- Frost Protect
- Find labor
- Total cost: approx. \$2,300/A



#### Step6: Pre-Harvest



Table 1. Critical temperatures of strawberries at various stages of flower development

Stage of Development	Critical Temp. (°F)
Tight bud	22.0
"Popcorn"	26.5
Open blossom	30.0
Fruit	28.0

Source: Perry, K.B. and E.B. Poling. 1986. Field observation of frost injury in strawberry buds and blossoms, Advances in Strawberry Production 5:31-38.

## **Tissue Sampling**

#### NC STATE UNIVERSITY

- Collect the most recently mature trifoliate leaves (MRML)
  - Has three leaflets and a petiole
  - Is full-sized and dark green
  - Is healthy--no diseases, insects or harsh environmental conditions (predictive)



#### **Tissue Sampling**

#### NC STATE UNIVERSITY

- Detach the petioles
  - Snap leaves off at the stem then separate the blades from the petioles



#### Measure NO3-N on petioles

A great predictor of soil N availability

#### **Tissue Sampling**



Growth	Week	NO <sub>3</sub> -N Sufficient	Nitrogen recommendation when petiole NO <sub>3</sub> -N				
Stage		Range (ppm)*	Below-	Within-	Above-		
			the sufficient range				
	1	600-1500			None		
	2-3	4000-6000		5.25 lb			
	4	3500-6000					
D / F	5-8	3000-5000	7 lb				
D/ Г	9	2000-4500	N/a/wk	IN/d/WK			
	10	2000-4000					
	11	1500-3000					
	12	1000-2000					

#### Information

- NC Strawberry Association: <u>https://ncstrawberry.com/</u>
- NCSU Strawberry Portal: <u>https://strawberries.ces.ncsu.edu/</u>
- Southern Regional IPM Center: <u>https://www.smallfruits.org/</u>
- NCDA & CS Agronomic Services: <u>http://www.ncagr.gov/agronomi/</u>
- Berry-Mg: Newsletter NCSU:

Email to: mj2@lists.ncsu.edu. Text in message body: 'subscribe berry-mg'

#### **NEW: Strawberry Youtube Channel:**

https://strawberries.ces.ncsu.edu/2019/08/strawberry-youtube-channel/

#### Thank you!



## Thank you for your attention

NCSU Department of Horticultural Science 2721 Founders Drive (Kilgore Hall), Room 258 Raleigh, 27695 NC

office (919) 513-0772 cell (919) 352 8006 Email: <u>mark.hoffmann@ncsu.edu</u> https://smallfruits.cals.ncsu.edu

